

5. Setting up the Users to access the store



Unlike mSupply Desktop, mSupply Mobile does not need or use individual user permissions for the store. All that is required is for the user to have login rights to the store.

5.01. Setting up Store access for Users



If you have used method [3.03 to create the store by cloning another sync store](#), the following steps are only required if you have further users to add.

At least one user needs to be added to the new store on the Primary server. The users will access the store from the device, but their credentials need to be set up on the Primary server.

To set up users on the Primary Server please refer to the mSupply User Guide [managing users](#).



When creating new users who will be using mSupply Mobile, consider the following to make them easier to enter on a tablet:

- Only use lower-case letters for both username and password
- Consider using short usernames and passwords
- **Strongly recommend** that you take care not to have trailing spaces at the end of the username or password


5.02. Setting up Store access for Admin Users

At least one Admin User needs to be set up to have access to the new store on the Primary server. This user will normally be the Susso1 user that was used to set up the new store, but there could well be other local mSupply administrators that need access.

1. Go to **Admin > Edit Users**



2. Select the user and go to **Login Rights**



3. Select the new Store

4. Click **OK**

5.03. Setting up Admin access to the device Settings

- To carry out various admin functions on the device, the logged in user needs the appropriate permission to access the mobile **Settings** page.
- You will likely *not* want the local users to have this permission. If that is the case, then an Admin user needs to be configured to have this permission.
- The Sustainable Solutions Susso^l is hard-wired *not* to have this permission. A special Sustainable Solutions user called Susso^lMobile can be set up to have this permission.

In the mSupply Central server:

1. Log into the mobile store
2. Go to File > Edit users
3. Select the mobile user (whom you want to give permission to access Settings - remember, not the Susso^l user 😊), double click it. An edit user window will open.
4. Go to **Permission (3)** tab and check the **View/edit preferences** permission on

The screenshot shows the 'Edit user' window with the following details:

- User:** Admin
- Store:** Hufflepuff Health Centre
- Tabs:** General, Permissions, Permissions (2), **Permissions (3)**, Login rights, Details, Dashboard
- Document management:**
 - Tenders:** Upload tender document, Download tender document, Delete tender document
 - Quotes:** Upload quote document, Download quote document, Delete quote document, Modify quotes entered by the supplier (via the website)
 - Items Lines (Batches of Stock):** Upload batch document, Download batch document, Delete batch document
 - Stocktakes:** Create stocktake, Delete stocktake, Add stocktake lines, View stocktake lines, Edit stocktake lines, Delete stocktake lines, Edit stocktake dates
- Virtual Stores:** Create new stores, Edit store details, Edit visibility in stores
- Reminders:** Edit and delete reminders assigned to me
- Admin:** Send email, Purge old records, View log, Set start of year stock, **View/edit preferences** (highlighted), Export & import, Backup data file
- Assets:** View assets, Add/edit assets, Setup assets
- Customer budgets:** Add/import customer budgets, Edit/delete customer budgets
- Registration:** Add/edit registrations, Change registration status
- Requisitions:** View requisitions, Create and edit requisitions, Administer finalised report type requisitions
- Supplier Hub:** View and edit supplier hub details (unchecked)

Buttons at the bottom: All on, Copy, Paste, Delete, Cancel, **OK**

Click **OK** to save it and again click **OK** to close **User list...** window.



Once these permissions are set, the **Settings** button will be visible the next time the user logs in to mSupply Mobile.

Previous: [4. Configuring the Store and Dispensing](#) | | Next: [6. Reviewing the setup](#)

From:
<https://wiki.msupply.foundation/> - mSupply Foundation Documentation

Permanent link:
https://wiki.msupply.foundation/en:mobile:setup:server_side:users?rev=1626389217

Last update: **2021/07/15 22:46**

